



PerfectScript COM integration does not work in WordPerfect® Office X5

- WordPerfect Office Suite

When attempting to add a reference to PerfectScript 15.0 through COM, you'll find that the PerfectScript entry is not present. The required PerfectScript registry keys are not written during the WordPerfect Office X5 installation.

To add the appropriate registry keys to your computer, do the following:

1. Save the attached Pfit.txt file to your desktop. (Save Pfit64.txt instead if you are using a 64-bit Windows® operating system.)
2. In this text file, find the following line:
[HKEY_LOCAL_MACHINE\SOFTWARE\Classes\TypeLib\{cc3ca09c-2090-46de-8b88-b697a77a5a84}\f.0\0\win3
HKEY_LOCAL_MACHINE\SOFTWARE\Classes\TypeLib\{cc3ca09c-2090-46de-8b88-b697a77a5a84}\f.0\0\win3
@="INSTALLDIR\ps150.exe\1"
3. In this line, replace INSTALLDIR with the installed location of WordPerfect Office X5.
IMPORTANT: Use double backslashes (\\) to mark folders. Ex. C:\\Program Files\\Corel\\WordPerfect Office X5
4. Save the text file as Pfit.reg
5. Double-click this file to add its entries to your registry.

The COM reference PerfectScript 15.0 should now be available.
